

# ColorDesigner PLUS v2.6 - Patch 4

---

## Contents of Patch

Patch 4 includes the following changes:

- On some computer systems, CD PLUS would crash when using a MatchRite iVue instrument (model number VS205).

Patch 4 includes everything in Patch 3:

- In certain cases, CD PLUS would not launch properly after Patch 2 was installed.

Patch 4 includes everything in Patch 2:


- In Color Lookup, some fandeck colors were omitted from the list. They are now included.
- Optional ability to explicitly obtain customer consent to store their data and to receive marketing communications.
- The connection between CD PLUS and its customer file database is now encrypted.

Patch 4 includes everything in Patch 1:

- When CD PLUS attempts to connect to a remote customer file database, it will try for up to 600 seconds. With the patch, it will try for 15 seconds. This connection timeout can be configured by IT professionals.
- When the operator searches the customer file database, CD PLUS will return all records, regardless of the number. This can negatively impact performance if the database contains hundreds of thousands of records. With the patch, it will return the first 100 records and will inform the user their search results have been limited. This setting can be configured by IT professionals.

## Installing the Patch


1. Download the patch and unzip it. Double click CDPPatch.exe to start the installation.



# ColorDesigner PLUS v2.6 - Patch 4

---

2. During the installation, you will see the following window. Wait for the installation to finish.



3. When the installation is finished, click **OK**.

