

ColorCert Version and Feature Compatibility

Rev. 180921

Rules

Compatibility	Details
2.7.0 and Above	If a custom dE formula has been used for the: <ol style="list-style-type: none"> 1. "Ink Adaption" dE Method <ul style="list-style-type: none"> • Gets baked into the Rule from Application Preferences 2. "Check Backing" dE Method 3. "Check Substrate" dE Method 4. "Check Primaries" dE Method 5. "Check Spot Colors" dE Method 6. "Check Undertones" dE Method
3.0.0 and Above	If a second or third Tolerance Method has been enabled or a new-to-v3 Tolerance Method has been selected (e.g. dL, da, ab, dCh, etc)
	If any Tolerance Methods have been set up for Grey Balances
	If any Tolerance Methods have been set up for Overprints
	If any Tolerance Values have been set up for C,M,Y or K Primaries
	If any Tolerance Values have been set up in the Dot Gain Primaries section
	If Dynamic G7 is enabled
	If any additional job details are set to mandatory
3.1.0 and Above	If any spot color tolerance methods have the 'For selected spot colors only' option checked.
	If Opacity tolerance is entered in Color Only Mode.
	If 'Whiteness' tolerance method is chosen for spot colors.
3.5.1 and Above	If Brightness tolerance method used.
	If Barcode checking is selected without visual checking.

Profiles

Compatibility	Details
2.7.0 and Above	If no Substrate or no Primaries are set up
	If a custom dE formula has been used for the "Ink Adaption" dE Method <ul style="list-style-type: none"> • Gets baked into the Profile from Application Preferences
3.0.0 and Above	If there are more than 8 Primaries or Spot Colors configured
	If any Primaries have a classification other than 'Other Primary' or any Spot Colors have a classification other than 'Spot'
3.1.0 and Above	If any spot colors have the 'Apply additional tolerance methods' option selected.

Jobs

Rules and profiles checked as listed above with the following additional checks...

Compatibility	Details
2.7.3 and Above	If a Custom Media Strip has been set up and it contains more than 48 patches
	If a Custom Media Strip has been set up and it contains skipped patches NOTE: There was a bug in the logic which meant that if the Default Media Strip was used, the Custom Media Strip <i>only</i> contained skipped patches and this was therefore wrongly interpreted as containing skipped patches leading to an error message

Applications

Rules and profiles checked as listed above (same as Jobs)...

CombiJobs

Compatibility	Details
3.1.0 and Above	Any combi job saved under 3.1.0 will be incompatible with previous versions due to the fact that the individual jobs are now packed inside the CCM file rather than being saved to a subfolder. This allows them to be saved to the repository.