

ColorDesigner PLUS v2.6 - Patch 6

Contents of Patch

Patch 6 includes the following changes:

- The list of colorants available in Manual Entry could differ, if an associated Electronic Formula Book and Color Matching Database contained slightly different colorants. Now Manual Entry will show the full set of colorants, regardless of whether the user selects the Electronic Formula Book or the Color Matching Database.
- Connection pooling for a remote customer file database can be configured by IT professionals.

Patch 6 includes everything in Patch 5:

- A side effect of Patch 4 was that Color Lookup took more time to complete a search. This has been corrected.

Patch 6 includes everything in Patch 4:

- On some computer systems, CD PLUS would crash when using a MatchRite iVue instrument (model number VS205).

Patch 6 includes everything in Patch 3:

- In certain cases, CD PLUS would not launch properly after Patch 2 was installed.

Patch 6 includes everything in Patch 2:

- In Color Lookup, some fandeck colors were omitted from the list. They are now included.
- Optional ability to explicitly obtain customer consent to store their data and to receive marketing communications.
- The connection between CD PLUS and its customer file database is now encrypted.


Patch 6 includes everything in Patch 1:

- When CD PLUS attempts to connect to a remote customer file database, it will try for up to 600 seconds. With the patch, it will try for 15 seconds. This connection timeout can be configured by IT professionals.
- When the operator searches the customer file database, CD PLUS will return all records, regardless of the number. This can negatively impact performance if the database contains hundreds of thousands of records. With the patch, it will return the first 100 records and will inform the user their search results have been limited. This setting can be configured by IT professionals.


ColorDesigner PLUS v2.6 - Patch 6

Installing the Patch

1. Download the patch and unzip it. Double click CDPPatch.exe to start the installation.



2. During the installation, you will see the following window. Wait for the installation to finish.



3. When the installation is finished, click **OK**.

